

BASIC SERIAL COMMAND SPECIFICATIONS

LC-XB40N

Ver 0.01

- CONTENTS	-
------------	---

1.	. (Ονε	erview				4
2.	. :	Ser	ial Interface Specifications				4
	2.1	۱.	Transfer Specifications	•••••			4
	2.2	2.	Connection	•••••			4
3.	. 1	Not	es for Communication				5
4	. 1	Fun	ctional Execution Command Table				6
5.		Stat	tus Read Command Table				8
6	. 1	Fun	ctional Execution Command				9
	6.1	۱.	Format	•••••			9
	6.2	2.	Command Pipelining	•••••			9
	6.3	3.	Transfer Example	•••••			9
	6.4	i .	Operation Requirements	•••••			10
	6.5	5.	POWER ON Command	•••••			11
	6.6	6.	POWER OFF Command (Quick Power OFF	•)			11
	6.7	7.	POWER OFF Command	•••••			11
	6.8	3.	Computer 1 (Digital) Command	•••••			11
	6.9).	Computer 2 Command	•••••			11
	6.1	0.	Video Command	•••••			12
	6.1	1.	VOLUME + Command	•••••			12
	6.1	2.	VOLUME – Command	•••••			12
	6.1	3.	AUDIO MUTE ON Command	•••••			12
	6.1	4.	AUDIO MUTE OFF Command	•••••			12
	6.1	5.	VIDEO MUTE ON Command	•••••			13
	6.1	6.	VIDEO MUTE OFF Command	•••••			13
	6.1	17.	Screen Normal size Command	•••••		•••••	13
	6.1	8.	Screen Wide size Command	•••••			13
	6.1	9.	Image Standard Command	•••••			13
	6.2	20.	Image Real Command	•••••		•••••	13
	6.2	21.	Image Cinema Command	•••••		•••••	14
	6.2	22.	Image1 Command	•••••		•••••	14
	6.2	23.	Image2 Command	•••••			14
	6.2	24.	Image3 Command	•••••		•••••	14
	6.2	25.	Image4 Command	•••••		•••••	14
	6.2	26.	Image Blackboard (Green) Command	•••••		•••••	14
		27.					
	-	28.	MENU ON Command				
	6.2	29.	MENU OFF Command	•••••		•••••	15
	6.3	30 .	DISPLAY CLEAR Command	•••••			15
						·	
ſ				Ver.	Rev.A	Page	1

6.31.	BRIGHTNESS + Command	•••••			15
6.32.	BRIGHTNESS – Command	•••••			15
6.33.	Computer 2 Component Command	•••••			16
6.34.	Computer 2 RGB Command	•••••			16
6.35.	Computer 2 SCART Command				16
6.36.	IMAGE (Toggle) Command				16
6.37.	ON START Setting Command				16
6.38.	ON START Cancel Command				16
6.39.	Power Management Ready Command				17
6.40.	Power Management OFF Command				17
6.41.	Power Management Shut down Command				17
6.42.	D.ZOOM + Command				17
6.43.	D.ZOOM – Command				17
6.44.	Video Auto Command				17
6.45.	Video Video Command				
6.46.	Video S-Video Command				18
6.47.	POINTER RIGHT Command	•••••		•••••	18
6.48.	POINTER LEFT Command	•••••			18
6.49.	POINTER UP Command	•••••			18
6.50.	POINTER DOWN Command	•••••		•••••	18
6.51.	ENTER Command				19
6.52.	FREEZE ON Command				19
6.53.	FREEZE OFF Command	•••••		•••••	19
6.54.	Computer 1 Analog RGB Command				19
6.55.	Computer 1 DVI (PC Digital) Command	•••••			19
6.56.	Computer 1 DVI (AV HDCP) Command	•••••			19
6.57.	PAGE UP Command				20
6.58.	PAGE DOWN Command	•••••		•••••	20
6.59.	INPUT WIRED Command	•••••			20
6.60.	INPUT WIRELESS Command	•••••			20
6.61.	INPUT VIEWER Command	•••••			20
6.62.	AUTO PC ADJ. Command				20
6.63.	PRESENTATION TIMER Command				21
6.64.	KEYSTONE Command				21
6.65.	KEYSTONE Command				21
7. Sta	tus Read Command				22
7.1.	Format				22
7.2.	Transfer Example	•••••			22
7.3.	Status Read Command	•••••		•••••	23
					
		Ver.	Rev.A	Page	2

7.4.	Input Mode Read Command	.25
7.5.	Lamp Time Read Command	.25
7.6.	Setting Read Command	.25
7.7.	Temp Read Command	. 26

		Ver.	Rev.A	Page	3
-	-			-	

1. Overview

- 1.1. These specifications define projector control commands for LC-XB40N (0.8" XGA).
- 1.2. The projector control commands are used to remotely control a projector through RS-232C from a computer.

2. Serial Interface Specifications

2.1. Transfer Specifications


Item	Specifications
Synchronous system	Asynchronous
Transmission Speed	9600 / 19200
Data Length	8 bit
Parity	N/A
Stop Bit	1
Flow Control	N/A

1) Transmission speed: initial setting value is 19200.

2) Transmission speed can be changed in service mode.

2.2. Connection

Dedicated serial cable must be used for connection to a computer and a projector.



	Ver.	Rev.A	Page	4
L				

3. Notes for Communication

- 1.1. The projector control command is defined as one command/one line that starts with "C" and ends with carriage return (0x0D).
- 2.2. There are two types of Commands: Functional Execution Commands and Status Read Commands.


Example of Functional Execution Command: "C05" [CR]

Example of Status Read Command: "CR0" [CR]

3.3. When it takes more than one second to receive one command, it does not operate.

The information of buffer is cleared when it takes more than one second to receive carriage return (0x0D) after the projector receives the first data "C".

4.4. For Command pipelining, wait for the interval of 100ms after receiving a response.



3.4.1. When a command is issued before receiving a response, the function is not executed properly.

3.4.2. Except for when there is no Response for more than 5 seconds.

- 5.5. It takes <u>about 5 seconds</u> for internal initialization after plugging in AC power. During this time, it cannot process commands. Do not issue any command.
- 6.6. The number of characters of response to Status Read Commands depends on commands. Please see [7. Status Read Commands].
- 7.7. Characters for commands must be Capital (A Z).

Ver. Re

4. Functional Execution Command Table

Command	Item	Command	Item
C00	POWER ON	C20	BRIGHTNESS +
C01	POWER OFF (Quick Power OFF)	C21	BRIGHTNESS -
C02	POWER OFF	C22	
C03		C23	
C04		C24	Computer 2 Component
C05	Computer 1 (Digital)	C25	Computer 2 RGB
C06	Computer 2	C26	Computer 2 Scart
C07	Video	C27	IMAGE (Toggle)
C08		C28	ON START Enable
C09	VOLUME +	C29	ON START Disable
C0A	VOLUME -	C2A	Power Management Ready
C0B	AUDIO MUTE ON	C2B	Power Management OFF
COC	AUDIO MUTE OFF	C2C	
COD	VIDEO MUTE ON	C2D	
C0E	VIDEO MUTE OFF	C2E	Power Management Shut down
C0F	Screen Normal size(4:3)	C2F	
C10	Screen Wide size(16:9)	C30	D.ZOOM +
C11	Image Standard	C31	D.ZOOM -
C12	Image Real	C32	Video Auto
C13	Image Cinema	C33	Video Video
C14	Image 1	C34	Video S-video
C15	Image 2	C35	
C16	Image 3	C36	
C17	Image 4	C37	
C18	Blackboard	C38	
C19	Dynamic	C39	
C1A		C3A	POINTER RIGHT
C1B		C3B	POINTER LEFT
C1C	MENU ON	C3C	POINTER UP
C1D	MENU OFF	C3D	POINTER DOWN
C1E	DISPLAY CLEAR	C3E	
C1F		C3F	ENTER

means no function.

	Ver.	Rev.A	Page	6
				2

Command	Item	Command	Item
C40		C80	
C41		C81	Input WIRED
C42		C82	Input WIRELESS
C43	FREEZE ON	C83	Input VIEWER
C44	FREEZE OFF	C84	
C45		C85	
C46		C86	
C47		C87	
C48		C88	
C49		C89	Auto PC ADJ.
C4A		C8A	PRESENTATION TIMER
C4B		C8B	
C4C		C8C	
C4D		C8D	
C4E		C8E	KEYSTONE
C4F		C8F	KEYSTONE
C50	Computer 1 Analog RGB	C90	
C51		C91	
C52	Computer 1 DVI (PC Digital)	C92	
C53	Computer 1 DVI (AV HDCP)	C93	
C54		C94	
C55		C95	
C56		C96	
C57		C97	
C58		C98	
C59	Page UP	C99	
C5A	Page DOWN	C9A	
C5B		C9B	
C5C		C9C	
C5D		C9D	
C5E		C9E	
C5F		C9F	

means no function.

	Ver.	Rev.A	Page	7
-	_	-	<u>.</u>	<i>.</i>

5. Status Read Command Table

Command	Item	Memo
CR0	Status Read	
CR1	Input Mode Read	
CR2		
CR3	(Corresponding) Lamp Time Read	
CR4	Setting Read	
CR5		
CR6	Temp Read	
CR7		
CR8		
CR9		
CRA		
CRB		
CRC		

means no function.

	Ver.	Rev.A	Page	8
			£	4

6. Functional Execution Command

6.1. Format

6.1.1. PC issues a command in format as below.

"C" COMMAND [CR]

Command: two characters (See Basic Functional Execution Command Table)

6.1.2. A projector changes received data to decode and returns a result after being ready to receive next command.

[ACK][CR]: (0x06, 0x0D) When received Functional Execution Commands.

6.1.3. "?"[CR]: When the received data cannot be decoded.


6.2. Command Pipelining

When some functions need the command pipelining, the performance is the same as that of the remote control;

- 6.2.1. System: issues any command every 100 ms.
- 6.2.2. When receiving the appropriate command, the function is executed for 120 ms from the moment.
- 6.2.3. When receiving the same command continuously within 120 ms, the function is executed for another 120 ms from the moment.
- 6.2.4. When there is no incoming command after 120 ms, the execution of pipelining is stopped.
- 6.2.5. When the projector receives other incoming commands within 120ms, the execution of pipelining is stopped.

6.3. Transfer Example

Switch the projector to video mode with Basic Command.



				
	Ver.	Rev.A	Page	9

6.4. Operation Requirements

When the projector's status in this below, Functional Execution Commands are limited.

Projector Status	Available Functional Execution Commands
Standby Mode	C00: POWER ON
	C00: POWER ON Countdown is terminated
Countdown in process	C01: POWER OFF
	C02: POWER OFF Countdown is terminated
Cooling Down in process	NONE
Cooling Down due to Abnormal Temperature	NONE
Abnormal Temperature Status	NONE
Power Save / Cooling Down in process	NONE
Power Save Status	C00: POWER ON
rower Save Status	C01: POWER OFF

Note) When the status is as above, even if the projector receives other commands,

it returns [ACK] [CR].

	Ver.	Rev.A	Page	10

6.5. POWER ON Command

Command	"C00" [CR]	
Detail		Power is ON, nothing is done. this command during processing Countdown, Countdown is
Response	Acceptable	[ACK] [CR]
Response	Unacceptable	" ? "[CR]

6.6. POWER OFF Command (Quick Power OFF)

Command	"C01" [CR]	
Detail	Power OFF (Standby) When Power is OFF with ON/STAND-BY button of the projector and remote control, "Power OFF?" is displayed. However, as soon as this command is sent Quick Power OFF is executed.	
Response	Acceptable	[ACK] [CR]
Response	Unacceptable	" ? "[CR]

6.7. POWER OFF Command

Command	"C02" [CR]	
Detail	of the projector Once this com again while it is	andby). operates the same Power OFF function as ON/STAND-BY button and remote control. mand is sent, "Power OFF?" is displayed. If this command is sent displayed, Power OFF is executed. this command during Countdown, Countdown is terminated.
Response	Acceptable	[ACK] [CR]
Response	Unacceptable	" ? "[CR]

6.8. Computer 1 (Digital) Command

Command	"C05" [CR]		
Detail	Select Compute	er 1(Digital) Input	
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.9. Computer 2 Command

Command	"C06" [CR]	"C06" [CR]		
Detail	Select Compute	er2 Input		
Response	Acceptable	[ACK] [CR]		
	Unacceptable	" ? "[CR]		

			Ver.	Rev.A	Page	11
--	--	--	------	-------	------	----

6.10. Video Command

Command	"C07" [CR]	"C07" [CR]		
Detail	Select Video In	put		
Pesnonse	Acceptable	[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

6.11. VOLUME + Command

Command	"C09" [CR]					
Detail	Volume Up. This command remote control.	This command operates the same way as "VOLUME+" button of the projector and				
Response	Acceptable	[ACK] [CR]				
Перопзе	Unacceptable	" ? "[CR]				

6.12. VOLUME – Command

Command	"C0A" [CR]				
Detail	Volume Down This command remote control.	This command operates the same way as "VOLUME-" button of the projector and			
Response	Acceptable	[ACK] [CR]			
Response	Unacceptable	" ? "[CR]			

6.13. AUDIO MUTE ON Command

Command	"C0B" [CR]	
Detail		N. works the same way as "MUTE" button of the remote control for loes not work for Mute OFF.
Response	Acceptable	[ACK] [CR]
Response	Unacceptable	" ? "[CR]

6.14. AUDIO MUTE OFF Command

Command	"C0C" [CR]	
Detail		FF. works the same way as "MUTE" button of the remote control for does not work for Mute ON.
Response	Acceptable	[ACK] [CR]
Пезропзе	Unacceptable	" ? "[CR]

			Ver.	Rev.A	Page	12
--	--	--	------	-------	------	----

6.15. VIDEO MUTE ON Command

Command	"C0D"[CR]				
Detail	This command	Video Mute ON. This command works the same way as "NO SHOW" button of the remote control for No Show ON, but does not work for No Show OFF.			
Response	Acceptable	[ACK] [CR]			
Response	Unacceptable	" ? "[CR]			

6.16. VIDEO MUTE OFF Command

Command	"C0E" [CR]				
Detail	This command	Video Mute OFF. This command works the same way as "NO SHOW" button of remote control for No Show OFF, but does not work for No Show ON.			
Response	Acceptable	[ACK] [CR]			
Response	Unacceptable	" ? "[CR]			

6.17. Screen Normal size Command

Command	"C0F" [CR]				
Detail		et screen size to Normal (4:3). his command is invalid while D.Zoom.			
Response	Acceptable	[ACK] [CR]			
	Unacceptable	" ? "[CR]			

6.18. Screen Wide size Command

Command	"C10" [CR]				
Detail		et screen size to Wide (16:9). his command is invalid while D.Zoom.			
Response	Acceptable	[ACK] [CR]			
	Unacceptable	" ? "[CR]			

6.19. Image Standard Command

Command	"C11" [CR]	C11" [CR]			
Detail	Set image to St	tandard mode.			
Response	Acceptable	[ACK] [CR]			
	Unacceptable	" ? "[CR]			

6.20. Image Real Command

Command	"C12" [CR]	C12" [CR]			
Detail	Set image to R	eal mode.			
Response	Acceptable	[ACK] [CR]			
	Unacceptable	" ? "[CR]			

0				
	Ver.	Rev.A	Page	13
-	,			

6.21. Image Cinema Command

Command	"C13" [CR]	
Detail	Set image to C	inema mode.
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

6.22. Image1 Command

Command	"C14" [CR]	
Detail	Set image to Im	nage1 mode.
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

6.23. Image2 Command

Command	"C15" [CR]	
Detail	Set image to In	nage2 mode.
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

6.24. Image3 Command

Command	"C16" [CR]		
Detail	Set image to In	nage3 mode.	
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.25. Image4 Command

Command	"C17" [CR]		
Detail	Set image to In	Set image to Image4 mode.	
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.26. Image Blackboard (Green) Command

Command	"C18" [CR]	
Detail	Set image to B	lackboard (Green) mode.
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

			Ver.	Rev.A	Page	14
--	--	--	------	-------	------	----

6.27. Image Dynamic Command

Command	"C19" [CR]		
Detail	Set image to Dy	namic mode.	
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.28. MENU ON Command

Command	"C1C" [CR]	
Detail	Display On-Scr	een Display Menu.
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

6.29. MENU OFF Command

Command	"C1D" [CR]		
Detail	Hide On-Scree	n Display Menu.	
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.30. DISPLAY CLEAR Command

Command	"C1E" [CR]		
Detail	Hide On-Screen Display. Hide On-Screen Display unconditionally.		
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.31. BRIGHTNESS + Command

Command	"C20" [CR]		
Detail	Brightness of U	lser Control +1.	
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.32. BRIGHTNESS - Command

Command	"C21" [CR]		
Detail	Brightness of User Control –1.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

			Ver.	Rev.A	Page	15
--	--	--	------	-------	------	----

6.33. Computer 2 Component Command

Command	"C24"[CR]		
Detail	Select Component input in Computer2.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.34. Computer 2 RGB Command

Command	"C25"[CR]		
Detail	Select RGB input in Computer2.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.35. Computer 2 SCART Command

Command	"C26"[CR]		
Detail	Select Scart input in Computer2.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.36. IMAGE (Toggle) Command

Command	"C27"[CR]			
Detail	0	Switch Image Setting status. This command works the same way as "IMAGE" button of the remote control.		
Response Acceptable [ACK] [CR]		[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

6.37. ON START Setting Command

Command	"C28" [CR]		
Detail	Enable Power ON Start. This status is stored in EEPROM and retained regardless of Power OFF/ON.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.38. ON START Cancel Command

Command	"C29" [CR]	"C29" [CR]		
Detail	Disable Power ON Start. This status is stored in EEPROM and retained regardless of Power OFF/ON.			
Response	Acceptable	[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

-	-	-	-	-	
		Ver.	Rev.A	Page	16
-	-	_	-		

6.39. Power Management Ready Command

Command	"C2A" [CR]	"C2A" [CR]		
Detail		Set Power Management to Ready mode. This status is stored in EEPROM and retained regardless of Power ON/OFF.		
Response Acceptable [ACK] [CR]		[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

6.40. Power Management OFF Command

Command	"C2B" [CR]			
Detail		Set Power Management to OFF mode. This status is stored in EEPROM and retained regardless of Power ON/OFF.		
Response Acceptable [ACK] [CR]		[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

6.41. Power Management Shut down Command

Command	"C2E" [CR]			
Detail		Set Power Management to Shut down mode. This status is stored in EEPROM and retained regardless of Power OFF/ON.		
Response	Acceptable	[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

6.42. D.ZOOM + Command

Command	"C30" [CR]		
Detail	Enter Digital Zoom mode and expand image size. This command works the same way as "D.ZOOM " button of the remote control.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.43. D.ZOOM – Command

Command	"C31" [CR]		
Detail	-	Enter Digital Zoom mode and reduce image size. This command works the same as "D.ZOOM " button of the remote control.	
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.44. Video Auto Command

Command	"C32" [CR]	
Detail	Select Auto input in Video.	
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

	Vor	Rev A	Page	17
	ver.	Nev.A	i aye	17

6.45. Video Video Command

Command	"C33" [CR]		
Detail	Select Video in	Select Video input in Video.	
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.46. Video S-Video Command

Command	"C34" [CR]		
Detail	Select S-Video	Select S-Video input in Video.	
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.47. POINTER RIGHT Command

Command	"C3A" [CR]	"C3A" [CR]		
Detail	Move the Pointer of On-Screen Display Menu to the right. This command works differently from the pointer ">" of the projector and has no function of Volume +.			
Response	Acceptable	[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

6.48. POINTER LEFT Command

Command	"C3B" [CR]	"C3B" [CR]	
Detail	Move the Pointer of On-Screen Display Menu to the left. This command works differently from the pointer "<" of the projector and has no function of Volume +.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.49. POINTER UP Command

Command	"C3C" [CR]	
Detail	Move up the Pointer of On-Screen Display Menu. This command works the same way as the pointer "" of the projector.	
Response	Acceptable	[ACK] [CR]
Response	Unacceptable	" ? "[CR]

6.50. POINTER DOWN Command

Command	"C3D" [CR]	"C3D" [CR]		
Detail	Move down the Pointer of On-Screen Display Menu. This command works the same way as the pointer "" of the projector.			
Response	Acceptable	[ACK] [CR]		
Response	Unacceptable	" ? "[CR]		

			Ver.	Rev.A	Page	18
--	--	--	------	-------	------	----

6.51. ENTER Command

Command	"C3F" [CR]		
Detail	This command works the same way as "SELECT" button of the projector and remote control.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.52. FREEZE ON Command

Command	"C43" [CR]		
Detail	Freeze on-screen image. This command works the same way as "FREEZE" button of the remote control for Freeze ON, but does not work for Freeze OFF.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

6.53. FREEZE OFF Command

Command	"C44" [CR]		
Detail	Cancel Freeze mode. This command works the same way as "FREEZE" button of the remote control for Freeze OFF, but does not work for Freeze ON.		
Response	Acceptable	[ACK] [CR]	
Пезропзе	Unacceptable	" ? "[CR]	

6.54. Computer 1 Analog RGB Command

Command	"C50" [CR]		
Detail	Select Analog RGB in Computer 1 input.		
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.55. Computer 1 DVI (PC Digital) Command

Command	"C52" [CR]		
Detail	Select DVI (PC Digital) in Computer 1 input 1.		
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.56. Computer 1 DVI (AV HDCP) Command

Command	"C53" [CR]	
Detail	Select DVI (AV HDCP) in Computer 1 input.	
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

			Ver.	Rev.A	Page	19
--	--	--	------	-------	------	----

6.57. PAGE UP Command

Command	"C59" [CR]		
Detail	Send the signal "Page Up" to PC when PC is connected to projector by USB.		
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.58. PAGE DOWN Command

Command	"C5A" [CR]		
Detail	Send the signal "Page Down" to PC when PC is connected to projector by USB.		
Response	Acceptable	[ACK] [CR]	
	Unacceptable	" ? "[CR]	

6.59. INPUT WIRED Command

Command	"C81" [CR]	
Detail	Select WIRED Input	
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

6.60. INPUT WIRELESS Command

Command	"C82" [CR]	
Detail	Select WIRELESS Input	
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

6.61. INPUT VIEWER Command

Command	"C83" [CR]	
Detail	Select VIEWER Input	
Response	Acceptable	[ACK] [CR]
	Unacceptable	" ? "[CR]

6.62. AUTO PC ADJ. Command

Command	"C89" [CR]		
Detail	Execute Auto PC Adj. function. This command works the same way as "AUTO PC ADJ." button of the remote control. Sending the command during Auto PC Adj. operation stops the operation. This is the same operation as "AUTO PC" button of the remote control.		
Response	Acceptable	[ACK] [CR]	
Response	Unacceptable	" ? "[CR]	

	1		Ver.	Rev.A	Page	20
--	---	--	------	-------	------	----

6.63. PRESENTATION TIMER Command

Command	"C8A" [CR]	"C8A" [CR]			
Detail	Execute Presentation Timer. This command works the same way as "P-TIMER" button of the remote control.				
Response	Acceptable	[ACK] [CR]			
Response	Unacceptable	" ? "[CR]			

6.64. KEYSTONE Command

Command	"C8E" [CR]			
Detail	Correct keystone distortion by reducing upper part of image.			
Response	Acceptable	[ACK] [CR]		
	Unacceptable	" ? "[CR]		

6.65. KEYSTONE Command

Command	"C8F" [CR]			
Detail Correct keystone distortion by reducing down part of image.				
Response	Acceptable	[ACK] [CR]		
	Unacceptable	" ? "[CR]		

6	-				
		Ver.	Rev.A	Page	21

7. Status Read Command

7.1. Format

7.1.1. PC issues commands in format as below;

"CR" Command [CR]

Command : 1 character (See Basic Status Read Command Table)

7.1.2. When a projector receives the appropriate command, it returns a character line as the

required data.


Required Data [CR]

Required Data : A character line (See Basic Status Read Command Table)

7.1.3. When the received data cannot be decoded, the projector returns "?" [CR].

7.2. Transfer Example

Get input mode for projector with basic commands



(Shows Computer 1 is selected)

-			_	-
	Ver.	Rev.A	Page	22
				6

7.3. Status Read Command

Command	"CR0" [CR]	"CR0" [CR]					
Detail	Get the project	Get the projector's operating status					
	Acceptable	"%1" [CR]					
Response	%1	 "00" = Power ON "80" = Standby "40" = Countdown in process "20" = Cooling Down in process "10" = Power Failure "28" = Cooling Down in process due to Temperature Anomaly "88" = Coming back after Temperature Anomaly "24" = Power Save/Cooling Down in process "04" = Power Save 					
	Unacceptable	"?" [CR]					

[Details of Response]

7.3.1. "00" [CR]

Status : Power ON

Normal image is on the screen.

7.3.2. "80" [CR]

Status: Standby

When the status is Standby, Status Read Commands are always acceptable, but Functional Execution Commands are not acceptable except POWER ON Command.

7.3.3. "40" [CR]

Status: Countdown in process

When "Display" in Setting Menu is ON and POWER ON is executed, it starts Countdown.

When "Display" in Setting Menu is OFF, processing Countdown is not executed and the status quickly moves to Power ON.

7.3.4. "20" [CR]

Status: Cooling Down in process

When the status is Power ON, and POWER OFF Command ("C01"[CR]) is executed, it moves to Cooling Down status.

This status automatically moves to Standby after lamp turns off and the fan spin finishes after about 90 seconds. The fan spin time depends on a model.

This function is used to cool down the lamps and other optical parts and is quite important for projector's reliability.

During this time, Functional Execution Commands are invalid.

Ver.	Rev.A	Page	23

7.3.5. "10" [CR]

Status: Power Failure

When the power supply voltage inside the projector reaches abnormal status, the projector is automatically turned off. The projector returns "10"[CR], which shows it moves to Power OFF status due to power failure. Fan also stops unlike Cooling Down status.

7.3.6. "28" [CR]

Status: Cooling Down in process due to Temperature Anomaly

When the inside temperature is out of the operating temperature, it automatically starts Cooling Down. Response for this status is "28"[CR].

Even if the temperature decreases during this process, Cooling Down is executed.

7.3.7. "88"[CR]

Status: Coming back after temperature anomaly

When the status moves to Standby after Cooling Down due to temperature anomaly, it returns "88" [CR].

This shows that the status turns to Standby because of abnormal temperature.

This status maintains until next operation is done. When Power On is executed, the information of temperature anomaly is canceled and normal operation is executed.

7.3.8. "24"[CR]

Status: Processing Power Save / Cooling Down

Power management function in Setting menu works and the status goes to Power Save / Cooling Down.

During this time, Functional Execution Commands are invalid (not executed).

This status moves to Power Save at set hours after the operation of Cooling Down.

Status: No signal	Power Save / Cooling Down	Power Save
Response∶ "00"	"24"	"04"
5 minutes v	vith no signal After a	T about 90 sec.

7.3.9. "04"[CR]

Status: Power Save

This shows that it moves to Power Save status by Power management function in Setting menu.

N	Ver.	Rev.A	Page	24

7.4. Input Mode Read Command

Command	"CR1" [CR]					
Detail	Get the selected Input No.					
	Acceptable	"%1" [CR]				
Response	%1	"1" = Computer 1 is selected "2" = Computer 2 is selected "3" = Video is selected "4" = Wired is selected "5" = Wireless/Viewer is selected				
	Unacceptable	"?" [CR]				

7.5. Lamp Time Read Command

Command	"CR3" [CR]	"CR3" [CR]				
Detail	Get the total lamp running hours (corresponding value).					
	Acceptable	"%1" [CR]				
Response	%1	Shows the time period with 5 digits numbers. Example: "00410"[CR] ····shows 410 hours				
	Unacceptable	"?" [CR]				

7.6. Setting Read Command

Command	"CR4" [CR]				
Detail	Get the screen setting status such as Ceiling / Rear.				
Response	Acceptable	"%1" [CR]			
	%1	"11"[CR] = Normal Screen Setting "10"[CR] = Picture is top/bottom reversed. (Status: Rear & Ceiling ON) "01"[CR] = Picture is left/right reversed. (Status: Rear ON) "00"[CR] = Picture is top/bottom and left/right reversed. (Status: Ceiling ON)			
	Unacceptable	"?" [CR]			

	Ver.	Rev.A	Page	25
-	-	-	-	_

7.7. Temp Read Command

Command	"CR6" [CR]				
Detail	Get the temperature data inside the projector. With some temperature sensors installed in the projector, it is possible to get all the temperature at once.				
	Acceptable	"%1_%2_%3" [CR]			
Response	%1 %2 %3	%1 = Temperature of sensor 1 %2 = Temperature of sensor 2 %3 = Temperature of sensor 3 Temperature data is shown as "00.0". When the temperature goes down to -, the first character becomes "-" instead of a space, like "-05.5" [CR]. When no temperature data can be returned due to hardware problems, the first character becomes "E" like"E00.0" [CR]. When several temperature sensors are equipped, Responses are returned continuously. "_31.535.233.4"[CR] The first data is sensor 1, then one space, and the data of sensor 2 follows.			
	Unacceptable	" ? "[CR]			

-				
	Ver.	Rev.A	Page	26